





Quilt project designed by Stephanie Prescott of A Quilter's Dream uses one Hoffman Bali Batiks fat-quarter bundle for the quilt top. Additional purchase of fabric for outer border and binding needed. Suggested are 1-3/8 yards of style # G2220-21-Teal for the outer border and 1/4 yard of style # 1895-551-Redwood for the binding. Quilt size is 50" X 69." Download this free pattern at www.HoffmanFabrics.com. Other patterns designed for Hoffman Bali Batiks fat-quarter bundles may be purchased from A Quilter's Dream. quilt@aquiltersdream.com 626-744-2779 www.aquiltersdream.com

Go With the Flow

Fabric Requirements:

Background: 9 fat quarters

Accents: 5 fat quarters

Backing: 2 2/3 yards (pieced horizontally)

Binding: 1/2 yard

Cutting Instructions:

Backgrounds:

Cut each of the 9 fat quarters as follows:

(ut (1) 3 1/2 inch strip

*** Turn remaining fat quarter so the 21 inch side is

horizontal and the 14 1/2 inch side is vertical.

Cut (8) 2 1/2 inch strips

Sub cut (6) of these strips into

(6) 2 1/2 x 12 1/2 units

Sub cut the remaining (2) strips into

 $(3) 2 1/2 \times 6 1/2$ inch units

You will have (9) unit stacks—1 for each background fabric

Accents:

Cut each of the 5 fat quarters as follows:

Cut(9) 1 1/2 inch strips

Sub cut (4) of these strips into

(12) 1 1/2 x 6 1/2 inch units

Sub cut (3) of these strips into


 $(12) 1 1/2 \times 4 1/2$ inch units


Leave the remaining (2) strips full length

Cut (2) 2 inch strips and sub cut into 2 inch

squares


You will have (5) unit stacks—1 for each accent fabric






Piecing Instructions:


- 1.) Take (1) background unit stack. Choose the (1) accent fabric stack you wish to use.
- 2.) Take (1) 2 1/2 x 6 1/2 inch background unit and (2) 1 1/2 x 6 1/2 inch accent units. Sew (1) accent unit to EACH 6 1/2 inch side of the background unit.
- 3.) Take (2) 1 1/2 x 4 1/2 inch accent units and sew (1) accent unit to EACH 4 1/2 side. (This is the rectangle unit and should measure 4 $1/2 \times 8 1/2$ inches.)




- 4.) Take the 3 1/2 inch background strip and sew (1) 1 1/2 inch full accent strip to one side of the background strip. Sub cut this sewn piece into (6) 2 $1/2 \times 4$ 1/2 inch units. (These are the direction units.)
- 5.) Take (1) direction unit. Position it so that the accent strip is on the right and sew to one 4 1/2 side of the rectangle unit. Take (1) direction unit and, positioning the accent strip to the right, sew to the opposite 4 1/2 inch side of the rectangle unit.
- 6.) Take (2) 2 $1/2 \times 12$ 1/2 inch background units and sew one along each of the 12 1/2 inch sides of your partial block.
- 7.) Square up block to 8 1/2 x 12 1/2.




- 8.) Take (1) 2 inch accent square from two different accent stacks. Holding the block with the
- 8 1/2 inch side horizontally, pin one accent square to the top left corner and the other accent square to the bottom right corner. The block should have one background fabric and 3 different accent fabrics (one for the main design and 2 for the corner squares).
- 9.) Sew pinned squares on to the corners of the block by sewing a diagonal line from point to point of the accent square. Once sewn, measure 1/4 inch from the sewn line towards the outside of the block and cut off the excess corners. Press the sewn triangle flaps to complete the outside corners of the block.
- 10.) Repeat steps #2-9 twice more with the same fabrics to yield 3 of the same blocks.





- 15 Blocks
- 11.) Put the remaining accent units back in the mix to be used in other blocks.
- 12.) Repeat steps #1-11 with (4) background stacks to yield a total of (15) blocks.

13.) Using the remaining (4) background stacks, repeat steps #1-11 as before EXCEPT that in step #5 change the direction of the unit to have the accent strip on the left and in step #8 sew the corner accent squares to the top right and bottom left. This will yield a total of (12) blocks.



12 Blocks